



# FMEA MANAGER

## Help Section

FMEA Dashboard

PROCESSUS Dashboard

Risk & Corrective action

Participant Profile


Team FMEA

Settings

Export datas

# FMEA Dashboard

This dashboard allows you to view the fmea that has been created, displaying the main information such as the number of participants, processes involved, potential risks depending on their level of criticality.




+ ADD

this button allows to add a new blank FMEA.

# Processus Dashboard

This dashboard describes all the stages of a production chain in chronological order. Each of these steps will contain all the potential risks attributed to it. Orange and red green color codes are defined based on the IPR rating and the predefined criticality level.



MANAGEMENT

this button allows to go to process management interface.




ADD Risk

this button allows to go to create a risk affiliated with a process



# Processus Builder



+ ADD Process

▲ ▼ Change Position

Inverse the position  
between two process



Change Process name




Process visibility

Process can't be deleted  
but can be hidden to be  
extracted from  
processus builder.



## Insert a risk



the viewpager allows you to  
scroll through the process  
steps from left to right. Click  
on the desired step to create  
a risk.

# Risk & Corrective action

These two interfaces make it possible to describe the potential risk as well as the corrective action to be implemented. They also have the scoring system for detectability, probability and severity to assess the risk level.

risk: at the bottom of the window, the button allows to erase the risk as well as the corrective action attached to it.

corrective action: at the bottom of the window, the button allows the administrator of the device to automatically request the designated manager, the actions performed and the update of the deadlines.

1:44

← RISK

Tony STARK

CORRECTIVE ACTION

1 STEP 1 Identification

08/05/2019 PART

Probleme de decoupe

Effect...

How to detect...

Root cause...

IPR LEVEL

100

SEVERITY 10

PROBABILITY 10

DETECTION 1

DELETE




SAVE

IMPORTANT : you must save your job, EditText and IPR before to leave in order to avoid to lose it.




Import Photo

opens an interface to import images and photos securely and confidentially. Touching the photo frame opens the viewpager for viewing or sorting.




## Define manager

Only fmea team participants can be selected to be affiliated with risk management or corrective action.



## Define Score



## Photo viewer





DELETE

after moving the photo to the trash, you must validate your choice by doing save and quit.

# Profile Section

The profile section allows to inform the user data. These are stored in the internal memory of the application in a completely secure manner, not subject to any dissemination to a third party application.

Main profile activation button allows you to define the user as administrator, and will automatically be designated as the team leader on the next creations of fmea.



+ ADD profile




PHOTO profile




# TEAM FMEA Section

The fmea team section allows each workgroup to be defined by the fmea to which it is attached. The group can not exceed 12 participants.

The designated participants in the team may be designated as a manager to lead the risk management or to take corrective action. The team will appear in the creation of the fmea report in the exports.



List of teams




Catalog of profile



# Settings

In settings, different levels of risk can be set according to the user's requirements.

The import of the logo of the company and its name allows to add a visual effect on the splash screen in portrait mode, with nothing more.



# Export data

The administrator of the application can send directly to his email address, the desired fmea report.

The file to be received will be of type \* .csv in order to be able to be reworked on excel software according to the standards of the users.

